

MT82W

Scan Engine

Serial Commands Manual

Chapter 1 Command List

Input: {head}{device ID}command}commandstatus}{package no.}{data

length}{data}{CRC16Check Digit} {end}

return: {head}{device ID}command}commandstatus}{package no.}{data

length}{data}{CRC16Check Digit} {end}

Note: The special description of the package label null is 0x00, the input head is 0x57 0x00, the input command status is 0x10, the returned head is 0x31 0x00, and the returned command status may be 0x10 (indicating that the setting is successful) or 0x11 (indicating that the setting is successful) fail).

| Type | Command | Data Length | | Function Description | Command |
|----------------|----------|-------------|-------------|-------------------------|--|
| System Setting | 02 01 00 | 04 00 | 01 00 00 00 | Enter Setting | 57 00 00 02 01 00 00 00 00 04 00 01 00 00 00 EA 7D 50 41 |
| | 02 01 00 | 04 00 | 00 00 00 00 | Exit Setting | 57 00 00 02 01 00 00 00 00 04 00 00 00 00 00 EB 81 50 41 |
| | 02 02 00 | 00 00 | null | Restore Factory Default | 57 00 00 02 02 00 00 00 00 00 00 B9 6C 50 41 |

| | | | | | |
|--|----------------|-------|-------------|-------------------------|--|
| | 02 04 00 | 04 00 | 00 00 00 00 | Save User Default | 57 00 00 02 04 00 00 00 00 04 00 00 00 00 00 00 FA 4D 50 41 |
| | 02 04 00 | 04 00 | 01 00 00 00 | Restore to User Default | 57 00 00 02 04 00 00 00 00 04 00 01 00 00 00 00 FB B1 50 41 |

| | | | | |
|----------------|-------|-------------|--|--|
| 02 05 00 | 04 00 | 00 00 00 00 | Set Reread Timeout to 500ms | 57 00 00 02 05 00 00 00 00 04 00 00 00 00 00 00 FE B1 50 41 |
| 02 05 00 | 04 00 | 01 00 00 00 | Set Reread Timeout to 750ms | 57 00 00 02 05 00 00 00 00 04 00 01 00 00 00 00 FF 4D 50 41 |
| 02 05 00 | 04 00 | 02 00 00 00 | Set Reread Timeout 1s | 57 00 00 02 05 00 00 00 00 04 00 02 00 00 00 00 FF 09 50 41 |
| 02 05 00 | 04 00 | 02 00 00 00 | Set Reread Timeout 2s | 57 00 00 02 05 00 00 00 00 04 00 03 00 00 00 00 FE F5 50 41 |
| 02 06 01 | 04 00 | 01 00 00 00 | Set Good Read Beep and Error Beep Volume to High | 57 00 00 02 06 01 00 00 00 04 00 01 00 00 00 00 A1 CC 50 41 |
| 02 06 01 | 04 00 | 00 00 00 00 | Set Good Read Beep and Error Beep Volume to Low | 57 00 00 02 06 01 00 00 00 04 00 00 00 00 00 00 A0 30 50 41 |
| 02 06 02 | 04 00 | 01 00 00 00 | Turn on Startup Beep | 57 00 00 02 06 02 00 00 00 04 00 01 00 00 00 00 51 C3 50 41 |
| 02 06 02 | 04 00 | 00 00 00 00 | Turn off Startup Beep | 57 00 00 02 06 02 00 00 00 04 00 00 00 00 00 00 50 3F 50 41 |
| 02 06 03 | 04 00 | 01 00 00 00 | Turn on Good Read Beep and Error Beep | 57 00 00 02 06 03 00 00 00 04 00 01 00 00 00 00 00 06 50 41 |
| 02 06 03 | 04 00 | 00 00 00 00 | Turn off Good Read Beep and Error Beep | 57 00 00 02 06 03 00 00 00 04 00 00 00 00 00 00 01 FA 50 41 |

| | | | | |
|----------------|-------|-------------|---|--|
| 02 06 04 | 04 00 | 00 00 00 00 | Set Good Read Beep Tone to Low | 57 00 00 02 06 04 00 00 00 04 00 00 00 00 00 00 B0 20 50 41 |
| 02 06 04 | 04 00 | 01 00 00 00 | Set Good Read Beep Tone to Medium | 57 00 00 02 06 04 00 00 00 04 00 01 00 00 00 00 B1 DC 50 41 |
| 02 06 04 | 04 00 | 02 00 00 00 | Set Good Read Beep Tone to High | 57 00 00 02 06 04 00 00 00 04 00 02 00 00 00 00 B1 98 50 41 |
| 02 06 05 | 04 00 | 01 00 00 00 | Set Good Read Beep and Error Beep Duration to Long | 57 00 00 02 06 05 00 00 00 04 00 01 00 00 00 00 E0 19 50 41 |
| 02 06 05 | 04 00 | 00 00 00 00 | Set Good Read Beep and Error Beep Duration to Short | 57 00 00 02 06 05 00 00 00 04 00 00 00 00 00 00 E1 E5 50 41 |
| 02 06 06 | 04 00 | 00 00 00 00 | Set Error Beep Tone to Low | 57 00 00 02 06 06 00 00 00 04 00 00 00 00 00 00 11 EA 50 41 |
| 02 06 06 | 04 00 | 01 00 00 00 | Set Error Beep Tone to Medium | 57 00 00 02 06 06 00 00 00 04 00 01 00 00 00 00 10 16 50 41 |
| 02 06 06 | 04 00 | 02 00 00 00 | Set Error Beep Tone to High | 57 00 00 02 06 06 00 00 00 04 00 02 00 00 00 00 10 52 50 41 |
| 02 06 07 | 04 00 | 01 00 00 00 | Turn on Command-Sending Beep | 57 00 00 02 06 07 00 00 00 04 00 01 00 00 00 00 41 D3 50 41 |
| 02 06 07 | 04 00 | 00 00 00 00 | Turn off Command-Sending Beep | 57 00 00 02 06 07 00 00 00 04 00 00 00 00 00 00 40 2F 50 41 |

| | | | | |
|----------------|-------|-------------|----------------------------------|---|
| 02 07 00 | 04 00 | 02 00 00 00 | Illumination LED Normal Mode | 57 00 00 02 07 00 00 00 00 04 00 02 00 00 00 F4 B1 50 41 |
| 02 07 00 | 04 00 | 01 00 00 00 | Set Illumination LED always on | 57 00 00 02 07 00 00 00 00 04 00 01 00 00 00 F4 F5 50 41 |
| 02 07 00 | 04 00 | 00 00 00 00 | Set Illumination LED always off | 57 00 00 02 07 00 00 00 00 04 00 00 00 00 00 F5 09 50 41 |
| 02 09 00 | 04 00 | 01 00 00 00 | Turn on Indicator LED | 57 00 00 02 09 00 00 00 00 04 00 01 00 00 00 C0 1D 50 41 |
| 02 09 00 | 04 00 | 00 00 00 00 | Turn off Indicator LED | 57 00 00 02 09 00 00 00 00 04 00 00 00 00 00 C1 E1 50 41 |
| 02 0D 01 | 04 00 | 00 00 00 00 | Disable Sleep Mode | 57 00 00 02 0D 01 00 00 00 04 00 00 00 00 00 85 14 50 41 |
| 02 0D 01 | 04 00 | 01 00 00 00 | Enable Sleep Mode | 57 00 00 02 0D 01 00 00 00 04 00 01 00 00 00 84 E8 50 41 |
| 02 0D 02 | 00 00 | Null | Enter Sleep Mode Now | 57 00 00 02 0D 02 00 00 00 00 00 47 8E 50 41 |
| 02 0D 03 | 04 00 | 0A 00 00 00 | Set Custom Timeout for Power off | 57 00 00 02 0D 03 00 00 00 04 00 0A 00 00 00 27 06 50 41 |
| 02 0E 00 | 04 00 | 01 00 00 00 | Enable Configuration Parameter | 57 00 00 02 0E 00 00 00 00 04 00 01 00 00 00 DA 69 50 41 |

| | | | | | |
|--------------|----------------|-------|-------------|--|--|
| | 02 0E 00 | 04 00 | 00 00 00 00 | Disable Configuration Parameter | 57 00 00 02 0E 00 00 00 00 04 00 00 00 00 00 00 DB 95 50 41 |
| Scan Mode | 03 01 01 | 00 00 | null | Auto-sensing Mode | 57 00 00 03 01 01 00 00 00 00 00 4A 71 50 41 |
| | 03 01 02 | 04 00 | 00 00 00 00 | Set Decode Session Timeout to Short | 57 00 00 03 01 02 00 00 00 04 00 00 00 00 00 00 B7 88 50 41 |
| | 03 01 02 | 04 00 | 01 00 00 00 | Set Decode Session Timeout to Medium | 57 00 00 03 01 02 00 00 00 04 00 01 00 00 00 00 B6 74 50 41 |
| | 03 01 02 | 04 00 | 02 00 00 00 | Set Decode Session Timeout to Long | 57 00 00 03 01 02 00 00 00 04 00 02 00 00 00 00 B6 30 50 41 |
| | 03 01 02 | 04 00 | 03 00 00 00 | Set Custom Decode Session Timeout | 57 00 00 03 01 02 00 00 00 04 00 03 00 00 00 00 B7 CC 50 41 |
| | 03 01 03 | 04 00 | 64 00 00 00 | 10s Set Decode Session Timeout to 10s | 57 00 00 03 01 03 00 00 00 04 00 64 00 00 00 00 F9 7D 50 41 |
| | 03 02 00 | 00 00 | null | Level Trigger Mode | 57 00 00 03 02 00 00 00 00 00 00 78 A0 50 41 |
| | 03 03 00 | 00 00 | null | Continuous Mode | 57 00 00 03 03 00 00 00 00 00 00 68 60 50 41 |
| | 03 04 01 | 00 00 | null | Host Mode | 57 00 00 03 04 01 00 00 00 00 00 1F 71 50 41 |

| | | | | | |
|--|----------------|-------|-------------|---|--|
| | 03 04 03 | 04 00 | 00 00 00 00 | Host Mode- Start Decoding | 57 00 00 03 04 03 00 00 00 04 00 00 00 00 00 00 F7 81 50 41 |
| | 03 04 03 | 04 00 | 01 00 00 00 | Host Mode- Stop Decoding | 57 00 00 03 04 03 00 00 00 04 00 01 00 00 00 00 F6 7d 50 41 |
| | 04 01 02 | 00 00 | Null | USB HID | 57 00 00 04 01 02 00 00 00 00 00 0B A4 50 41 |
| | 04 01 03 | 04 00 | 01 00 00 00 | (Appendix 2) Enable Control Character Escape | 57 00 00 04 01 03 00 00 00 04 00 01 00 00 00 00 12 7A 50 41 |
| | 04 01 03 | 04 00 | 00 00 00 00 | Disable Control Character Escape | 57 00 00 04 01 03 00 00 00 04 00 00 00 00 00 00 13 86 50 41 |
| | 04 01 04 | 04 00 | 00 00 00 00 | Do not Replace GS character | 57 00 00 04 01 04 00 00 00 04 00 00 00 00 00 00 A2 5C 50 41 |
| | 04 01 04 | 04 00 | 01 00 00 00 | Replace GS character to Ç | 57 00 00 04 01 04 00 00 00 04 00 01 00 00 00 00 A3 A0 50 41 |
| | 04 01 04 | 04 00 | 02 00 00 00 | Replace GS character to | 57 00 00 04 01 04 00 00 00 04 00 02 00 00 00 00 A3 E4 50 41 |
| | 04 01 04 | 04 00 | 03 00 00 00 | Replace GS character to ^] | 57 00 00 04 01 04 00 00 00 04 00 03 00 00 00 00 A2 18 50 41 |
| | 04 01 04 | 04 00 | 04 00 00 00 | Replace GS character to] | 57 00 00 04 01 04 00 00 00 04 00 04 00 00 00 00 A3 6C 50 41 |

| | | | | |
|----------------|-------|-------------|---|---|
| 04 01 04 | 04 00 | 05 00 00 00 | Replace GS character to <GS> | 57 00 00 04 01 04 00 00 00 04 00 05 00 00 00 A2 90 50 41 |
| 04 01 08 | 04 00 | 00 00 00 00 | Disable Virtual Keyboard | 57 00 00 04 01 08 00 00 00 04 00 00 00 00 00 62 63 50 41 |
| 04 01 08 | 04 00 | 01 00 00 00 | Enable Virtual Keyboard (Mode 一) | 57 00 00 04 01 08 00 00 00 04 00 01 00 00 00 63 9F 50 41 |
| 04 01 08 | 04 00 | 02 00 00 00 | Enable Virtual Keyboard (Mode 二) | 57 00 00 04 01 08 00 00 00 04 00 02 00 00 00 63 DB 50 41 |
| 04 01 08 | 04 00 | 03 00 00 00 | Enable Virtual Keyboard (Mode 三) | 57 00 00 04 01 08 00 00 00 04 00 03 00 00 00 62 27 50 41 |
| 04 01 09 | 01 00 | 00 | Set Transmission Speed-USB Keyboard to Low | 57 00 00 04 01 09 00 00 00 01 00 00 0E C7 50 41 |
| 04 01 09 | 01 00 | 01 | Set Transmission Speed-USB Keyboard to Medium | 57 00 00 04 01 09 00 00 00 01 00 01 CF 07 50 41 |
| 04 01 09 | 01 00 | 02 | Set Transmission Speed-USB Keyboard to High | 57 00 00 04 01 09 00 00 00 01 00 02 8F 06 50 41 |
| 04 01 09 | 01 00 | 03 | Set Custom Transmission Speed-USB Keyboard | 57 00 00 04 01 09 00 00 00 01 00 03 4E C6 50 41 |
| 04 01 0A | 04 00 | 0A 00 00 00 | Set Transmission Speed-USB Keyboard to 10ms | 57 00 00 04 01 0A 00 00 00 04 00 0A 00 00 00 C0 71 50 41 |

| | | | | |
|----------------|-------|-------------|---|---|
| 04 01 0C | 04 00 | 01 00 00 00 | Set Country Keyboard to America(English) | 57 00 00 04 01 0C 00 00 00 04 00 01 00 00 00 22 4A 50 41 |
| 04 01 0C | 04 00 | 03 00 00 00 | Set Country Keyboard to Italian | 57 00 00 04 01 0C 00 00 00 04 00 03 00 00 00 23 F2 50 41 |
| 04 01 0C | 04 00 | 06 00 00 00 | Set Country Keyboard to Spanish(Brazil) | 57 00 00 04 01 0C 00 00 00 04 00 06 00 00 00 23 3E 50 41 |
| 04 01 0C | 04 00 | 12 00 00 00 | Set Country Keyboard to Portuguese(Portuguese) | 57 00 00 04 01 0C 00 00 00 04 00 12 00 00 00 26 CE 50 41 |
| 04 01 0C | 04 00 | 13 00 00 00 | Set Country Keyboard to Brazil(Portuguese) | 57 00 00 04 01 0C 00 00 00 04 00 13 00 00 00 27 32 50 41 |
| 04 01 0C | 04 00 | 18 00 00 00 | Set Country Keyboard to French | 57 00 00 04 01 0C 00 00 00 04 00 18 00 00 00 25 16 50 41 |
| 04 01 0C | 04 00 | 19 00 00 00 | Set Country Keyboard to German(Austria) | 57 00 00 04 01 0C 00 00 00 04 00 19 00 00 00 24 EA 50 41 |
| 04 01 0C | 04 00 | 15 00 00 00 | Set Country Keyboard to Turkish Q | 57 00 00 04 01 0C 00 00 00 04 00 15 00 00 00 27 BA 50 41 |
| 04 01 0C | 04 00 | 16 00 00 00 | Set Country Keyboard to Turkish F | 57 00 00 04 01 0C 00 00 00 04 00 16 00 00 00 27 FE 50 41 |
| 04 01 0C | 04 00 | 1B 00 00 00 | Set Country Keyboard to UK-English | 57 00 00 04 01 0C 00 00 00 04 00 1B 00 00 00 25 52 50 41 |

| | | | | | |
|--|----------------|-------|-------------|---------------------------------------|---|
| | 04 01 0C | 04 00 | 09 00 00 00 | Set Country Keyboard to Japanese | 57 00 00 04 01 0C 00 00 00 04 00 09 00 00 00 20 2A 50 41 |
| | 04 01 0C | 04 00 | 1A 00 00 00 | Set Country Keyboard to Swiss(German) | 57 00 00 04 01 0C 00 00 00 04 00 1A 00 00 00 24 AE 50 41 |
| | 04 01 0D | 00 00 | Null | USB CDC | 57 00 00 04 01 0D 00 00 00 00 00 0B 5B 50 41 |
| | 04 02 01 | 00 00 | null | RS-232 | 57 00 00 04 02 01 00 00 00 00 00 38 97 50 41 |
| | 04 02 02 | 00 00 | null | RS-485 | 57 00 00 04 02 02 00 00 00 00 00 38 A4 50 41 |
| | 04 02 03 | 01 00 | 01 | RS-485 Device ID 0x01 | 57 00 00 04 02 03 00 00 00 01 00 01 25 12 50 41 |
| | 04 02 04 | 04 00 | 00 00 00 00 | Baud Rate: 4800 | 57 00 00 04 02 04 00 00 00 04 00 00 00 00 00 AD 18 50 41 |
| | 04 02 04 | 04 00 | 01 00 00 00 | Baud Rate: 9600 | 57 00 00 04 02 04 00 00 00 04 00 01 00 00 00 AC E4 50 41 |
| | 04 02 04 | 04 00 | 02 00 00 00 | Baud Rate: 19200 | 57 00 00 04 02 04 00 00 00 04 00 02 00 00 00 AC A0 50 41 |
| | 04 02 04 | 04 00 | 03 00 00 00 | Baud Rate: 38400 | 57 00 00 04 02 04 00 00 00 04 00 03 00 00 00 AD 5C 50 41 |

| | | | | |
|----|-------|-------------|--|---|
| 04 | 04 00 | 04 00 00 00 | Baud Rate : 57600 | 57 00 00 04 02 04 00 00 00 04 00 04 00 00 00 AC 28 50 41 |
| 02 | 04 00 | 05 00 00 00 | Baud Rate: 115200 | 57 00 00 04 02 04 00 00 00 04 00 05 00 00 00 AD D4 50 41 |
| 04 | 04 00 | 06 00 00 00 | Data Bit 8, Stop Bit 1, No Parity | 57 00 00 04 02 05 00 00 00 04 00 06 00 00 00 FC 55 50 41 |
| 02 | 04 00 | 07 00 00 00 | Data Bit 8, Stop Bit 1, Odd Parity | 57 00 00 04 02 05 00 00 00 04 00 07 00 00 00 FD A9 50 41 |
| 05 | 04 00 | 08 00 00 00 | Data Bit 8, Stop Bit 1, Even Parity | 57 00 00 04 02 05 00 00 00 04 00 08 00 00 00 FE BD 50 41 |
| 04 | 04 00 | 09 00 00 00 | Data Bit 8, Stop Bit 2, No Parity | 57 00 00 04 02 05 00 00 00 04 00 09 00 00 00 FF 41 50 41 |
| 02 | 04 00 | 0A 00 00 00 | Data Bit 8, Stop Bit 2, Odd Parity | 57 00 00 04 02 05 00 00 00 04 00 0A 00 00 00 FF 05 50 41 |
| 05 | 04 00 | 0B 00 00 00 | Data Bit 8, Stop Bit 2, Even Parity | 57 00 00 04 02 05 00 00 00 04 00 0B 00 00 00 FE F9 50 41 |
| 04 | 04 00 | 00 00 00 00 | Set Serial Decode Format to origin data | 57 00 00 04 02 06 00 00 00 04 00 00 00 00 00 0C D2 50 41 |
| 02 | 04 00 | 01 00 00 00 | Set Serial Decode Format to UTF-8 | 57 00 00 04 02 06 00 00 00 04 00 01 00 00 00 0D 2E 50 41 |
| 06 | | | | |

| | | | | | |
|----------------|----------------|-------|-------------|---|---|
| | 04 02 06 | 04 00 | 02 00 00 00 | Set Serial Decode Format to GBK | 57 00 00 04 02 06 00 00 00 04 00 02 00 00 00 0D 6A 50 41 |
| | 04 03 01 | 00 00 | null | Wiegand Interface | 57 00 00 04 03 01 00 00 00 00 00 28 57 50 41 |
| | 04 03 02 | 04 00 | 00 00 00 00 | Wiegand 26 | 57 00 00 04 03 02 00 00 00 04 00 00 00 00 00 49 FB 50 41 |
| | 04 03 02 | 04 00 | 01 00 00 00 | Wiegand 34 | 57 00 00 04 03 02 00 00 00 04 00 01 00 00 00 48 07 50 41 |
| Data Format | 05 01 01 | 04 00 | 01 00 00 00 | Enable Custom Prefix | 57 00 00 05 01 01 00 00 00 04 00 01 00 00 00 4E 73 50 41 |
| | 05 01 01 | 04 00 | 00 00 00 00 | Disable Custom Prefix | 57 00 00 05 01 01 00 00 00 04 00 00 00 00 00 4F 8F 50 41 |
| | 05 01 02 | 00 00 | null | Clear Custom Prefix | 57 00 00 05 01 02 00 00 00 00 00 CA 68 50 41 |
| | 05 01 03 | 02 00 | 99 61 | Example: Set Custom Prefix "a"(hex:6 1) to all symbolologies (hex:99) | 57 00 00 05 01 03 00 00 00 02 00 99 61 3C 82 50 41 |
| | 05 02 01 | 04 00 | 01 00 00 00 | Enable Custom Suffix | 57 00 00 05 02 01 00 00 00 04 00 01 00 00 00 41 37 50 41 |
| | 05 02 01 | 04 00 | 00 00 00 00 | Disable Custom Suffix | 57 00 00 05 02 01 00 00 00 04 00 00 00 00 00 40 CB 50 41 |

| | | | | |
|----------------|-------|-------------|--|---|
| 05 02 02 | 00 00 | null | Clear Custom Suffix | 57 00 00 05 02 02 00 00 00 00 00 F9 68 50 41 |
| 05 02 03 | 02 00 | 99 61 | Example :Set Custom Suffix "a"(hex:6 1) to all sybologies (hex:99) | 57 00 00 05 02 03 00 00 00 02 00 99 61 28 72 50 41 |
| 05 03 01 | 04 00 | 00 00 00 00 | Disable CODE ID | 57 00 00 05 03 01 00 00 00 04 00 00 00 00 00 44 37 50 41 |
| 05 03 01 | 04 00 | 01 00 00 00 | Enable CODE ID Prefix | 57 00 00 05 03 01 00 00 00 04 00 01 00 00 00 45 CB 50 41 |
| 05 03 01 | 04 00 | 02 00 00 00 | Enable CODE ID Suffix | 57 00 00 05 03 01 00 00 00 04 00 02 00 00 00 45 8F 50 41 |
| 05 03 02 | 00 00 | null | Clear CODE ID | 57 00 00 05 03 02 00 00 00 00 00 E9 A8 50 41 |
| 05 03 03 | 02 00 | 61 59 | Set Custom CODE ID, Example: Set Codabar CodeID (appendix 1) to "Y" (appendix 3) | 57 00 00 05 03 03 00 00 00 02 00 61 59 67 F0 50 41 |
| 05 04 00 | 04 00 | 00 00 00 00 | Disable AIM ID | 57 00 00 05 04 00 00 00 00 04 00 00 00 00 00 0F 86 50 41 |
| 05 04 00 | 04 00 | 01 00 00 00 | Enable AIM ID Prefix | 57 00 00 05 04 00 00 00 00 04 00 01 00 00 00 0E 7A 50 41 |
| 05 04 00 | 04 00 | 02 00 00 00 | Enable AIM ID Sufix | 57 00 00 05 04 00 00 00 00 04 00 02 00 00 00 0E 3E 50 41 |

| | | | | |
|----------------|-------|-------------|--|--|
| 05 | 04 00 | 00 00 00 00 | No Start Character | 57 00 00 05 05 00 00 00 00 04 00 00 00 00 00 00 0B 7A 50 41 |
| 05 05 00 | 04 00 | 01 00 00 00 | Set Start Character to STX | 57 00 00 05 05 00 00 00 00 04 00 01 00 00 00 00 0A 86 50 41 |
| 05 06 00 | 04 00 | 00 00 00 00 | Set Terminator as CR (Enter) | 57 00 00 05 06 00 00 00 00 04 00 00 00 00 00 00 04 3E 50 41 |
| 05 06 00 | 04 00 | 01 00 00 00 | Set Terminator as LF (Down) | 57 00 00 05 06 00 00 00 00 04 00 01 00 00 00 00 05 C2 50 41 |
| 05 06 00 | 04 00 | 02 00 00 00 | Set Terminator as CR+LF (Enter+Down) | 57 00 00 05 06 00 00 00 00 04 00 02 00 00 00 00 05 86 50 41 |
| 05 06 00 | 04 00 | 03 00 00 00 | Set Terminator as Tab | 57 00 00 05 06 00 00 00 00 04 00 03 00 00 00 00 04 7A 50 41 |
| 05 06 00 | 04 00 | 04 00 00 00 | Set Terminator as ETX | 57 00 00 05 06 00 00 00 00 04 00 04 00 00 00 00 05 0E 50 41 |
| 05 06 00 | 04 00 | 05 00 00 00 | No Terminator Suffix | 57 00 00 05 06 00 00 00 00 04 00 05 00 00 00 00 04 F2 50 41 |
| 05 07 01 | 04 00 | 00 00 00 00 | Set Prefix sequence : Start Character+CODE ID+AIM ID+Custom Prefix | 57 00 00 05 07 01 00 00 00 04 00 00 00 00 00 00 51 07 50 41 |
| 05 07 01 | 04 00 | 01 00 00 00 | Set Prefix sequence: Start Character+Custom Prefix+CODE ID+AIM ID | 57 00 00 05 07 01 00 00 00 04 00 01 00 00 00 00 50 FB 50 41 |

| | | | | |
|----------------|-------|-------------|--|---|
| 05 07 02 | 04 00 | 00 00 00 00 | Set Suffix sequence: Custom Suffix+CODE ID+AIM ID+Terminator Suffix | 57 00 00 05 07 02 00 00 00 04 00 00 00 00 00 A1 08 50 41 |
| 05 07 02 | 04 00 | 01 00 00 00 | Set Suffix sequence: CODE ID+AIM ID+Custom Suffix+Terminator Suffix | 57 00 00 05 07 02 00 00 00 04 00 01 00 00 00 A0 F4 50 41 |
| 05 08 00 | 04 00 | 00 00 00 00 | Do not Convert Case | 57 00 00 05 08 00 00 00 00 04 00 00 00 00 00 30 D6 50 41 |
| 05 08 00 | 04 00 | 01 00 00 00 | Convert Case | 57 00 00 05 08 00 00 00 00 04 00 01 00 00 00 31 2A 50 41 |
| 05 08 00 | 04 00 | 02 00 00 00 | Convert all to Upper Case | 57 00 00 05 08 00 00 00 00 04 00 02 00 00 00 31 6E 50 41 |
| 05 08 00 | 04 00 | 03 00 00 00 | Convert all to Lower Case | 57 00 00 05 08 00 00 00 00 04 00 03 00 00 00 30 92 50 41 |
| 05 09 01 | 04 00 | 00 00 00 00 | Transmit Origin Decoded Data | 57 00 00 05 09 01 00 00 00 04 00 00 00 00 00 65 EF 50 41 |
| 05 09 01 | 04 00 | 01 00 00 00 | Transmit start data | 57 00 00 05 09 01 00 00 00 04 00 01 00 00 00 64 13 50 41 |
| 05 09 01 | 04 00 | 02 00 00 00 | Transmit Center Data | 57 00 00 05 09 01 00 00 00 04 00 02 00 00 00 64 57 50 41 |

| | | | | | |
|-----------------------|----------------|-------|-------------|--------------------------------|---|
| | 05 09 01 | 04 00 | 03 00 00 00 | Transmit End Data | 57 00 00 05 09 01 00 00 00 04 00 03 00 00 00 65 AB 50 41 |
| | 05 09 01 | 04 00 | 04 00 00 00 | Transmit Start and End Data | 57 00 00 05 09 01 00 00 00 04 00 04 00 00 00 64 DF 50 41 |
| | 05 09 02 | 04 00 | 03 00 00 00 | Set Start Data Length to 3 | 57 00 00 05 09 02 00 00 00 04 00 03 00 00 00 95 A4 50 41 |
| | 05 09 03 | 04 00 | 04 00 00 00 | Set End Data Length to 4 | 57 00 00 05 09 03 00 00 00 04 00 04 00 00 00 C5 15 50 41 |
| | 05 0A 00 | 00 00 | null | Clear Cache Data | 57 00 00 05 0A 00 00 00 00 00 00 71 4A 50 41 |
| 解 码 库 设 置 | 06 01 00 | 04 00 | 01 00 00 00 | Enable All Symbologies | 57 00 00 06 01 00 00 00 00 04 00 01 00 00 00 1B B2 50 41 |
| | 06 01 00 | 04 00 | 00 00 00 00 | Disable All Symbologies | 57 00 00 06 01 00 00 00 00 04 00 00 00 00 00 1A 4E 50 41 |
| | 06 02 00 | 04 00 | 01 00 00 00 | Enable All 1D Symbologies | 57 00 00 06 02 00 00 00 00 04 00 01 00 00 00 14 F6 50 41 |
| | 06 02 00 | 04 00 | 00 00 00 00 | Disable All 1D Symbologies | 57 00 00 06 02 00 00 00 00 04 00 00 00 00 00 15 0A 50 41 |
| | 06 03 00 | 04 00 | 01 00 00 00 | Enable All 2D Symbologies | 57 00 00 06 03 00 00 00 00 04 00 01 00 00 00 10 0A 50 41 |

| | | | | | |
|--|----------------|-------|-------------|--|--|
| | 06 03 00 | 04 00 | 00 00 00 00 | Disable All 2D Symbologies | 57 00 00 06 03 00 00 00 00 04 00 00 00 00 00 00 11 F6 50 41 |
| | 06 04 00 | 04 00 | 00 00 00 00 | Only Decode Regular Bar Codes | 57 00 00 06 04 00 00 00 00 04 00 00 00 00 00 00 0B 82 50 41 |
| | 06 04 00 | 04 00 | 01 00 00 00 | Only Decode Inverse Bar Codes | 57 00 00 06 04 00 00 00 00 04 00 01 00 00 00 00 0A 7E 50 41 |
| | 06 04 00 | 04 00 | 02 00 00 00 | Decode Both Regular and Inverse Bar Codes | 57 00 00 06 04 00 00 00 00 04 00 02 00 00 00 00 0A 3A 50 41 |
| | 06 05 01 | 04 00 | 01 00 00 00 | Enable Codabar | 57 00 00 06 05 01 00 00 00 04 00 01 00 00 00 00 5F 47 50 41 |
| | 06 05 01 | 04 00 | 00 00 00 00 | Disable Codabar | 57 00 00 06 05 01 00 00 00 04 00 00 00 00 00 00 5E BB 50 41 |
| | 06 05 02 | 04 00 | 01 00 00 00 | Codaba Start/Stop Character Enable | 57 00 00 06 05 02 00 00 00 04 00 01 00 00 00 00 AF 48 50 41 |
| | 06 05 02 | 04 00 | 00 00 00 00 | Codaba Start/Stop Character Disable | 57 00 00 06 05 02 00 00 00 04 00 00 00 00 00 00 AE B4 50 41 |
| | 06 05 03 | 02 00 | 08 0C | Example : Set Length Range 8-12 for Codabar | 57 00 00 06 05 03 00 00 00 02 00 08 0C 52 30 50 41 |
| | 06 06 01 | 04 00 | 01 00 00 00 | Enable Codo 39 | 57 00 00 06 06 01 00 00 00 04 00 01 00 00 00 00 50 03 50 41 |

| | | | | |
|----------------|-------|-------------|--|--|
| 06 06 01 | 04 00 | 00 00 00 00 | Disable Codo 39 | 57 00 00 06 06 01 00 00 00 04 00 00 00 00 00 00 51 FF 50 41 |
| 06 06 02 | 04 00 | 00 00 00 00 | Disable Code 39 Check Digit | 57 00 00 06 06 02 00 00 00 04 00 00 00 00 00 00 A1 F0 50 41 |
| 06 06 02 | 04 00 | 01 00 00 00 | Enable but Do not Transmit Code 39 Check Digit | 57 00 00 06 06 02 00 00 00 04 00 01 00 00 00 A0 0C 50 41 |
| 06 06 02 | 04 00 | 02 00 00 00 | Enable and Transmit Code 39 Check Digit | 57 00 00 06 06 02 00 00 00 04 00 02 00 00 00 A0 48 50 41 |
| 06 06 03 | 04 00 | 00 00 00 00 | Disable Code 39 Full ASCII | 57 00 00 06 06 03 00 00 00 04 00 00 00 00 00 00 F0 35 50 41 |
| 06 06 03 | 04 00 | 01 00 00 00 | Enable Code 39 Full ASCII | 57 00 00 06 06 03 00 00 00 04 00 01 00 00 00 F1 C9 50 41 |
| 06 06 04 | 02 00 | 08 0C | Example : Set Length Range 8-12 for Code 39 | 57 00 00 06 06 04 00 00 00 02 00 08 0C 07 26 50 41 |
| 06 07 00 | 04 00 | 01 00 00 00 | Enable Code 32 | 57 00 00 06 07 00 00 00 00 04 00 01 00 00 00 05 3A 50 41 |
| 06 07 00 | 04 00 | 00 00 00 00 | Disable Code 32 | 57 00 00 06 07 00 00 00 00 04 00 00 00 00 00 04 C6 50 41 |
| 06 08 01 | 04 00 | 01 00 00 00 | Enable Interleaved 2 of 5 (ITF5) | 57 00 00 06 08 01 00 00 00 04 00 01 00 00 00 64 EB 50 41 |

| | | | | |
|----------------|-------|-------------|---|--|
| 06 08 01 | 04 00 | 00 00 00 00 | Disable Interleaved 2 of 5 (ITF5) | 57 00 00 06 08 01 00 00 00 04 00 00 00 00 00 00 65 17 50 41 |
| 06 08 02 | 04 00 | 00 00 00 00 | Interleaved 2 of 5 (ITF5) Disable Check Digit | 57 00 00 06 08 02 00 00 00 04 00 00 00 00 00 00 95 18 50 41 |
| 06 08 02 | 04 00 | 01 00 00 00 | Enable but do not Transmit Interleaved 2 of 5 Check Digit | 57 00 00 06 08 02 00 00 00 04 00 01 00 00 00 00 94 E4 50 41 |
| 06 08 02 | 04 00 | 02 00 00 00 | Enable and Transmit Interleaved 2 of 5 Check Digit | 57 00 00 06 08 02 00 00 00 04 00 02 00 00 00 00 94 A0 50 41 |
| 06 08 03 | 04 00 | 00 00 00 00 | Interleaved 2 of 5 (ITF5) Any Length (4-128) | 57 00 00 06 08 03 00 00 00 04 00 00 00 00 00 00 C4 DD 50 41 |
| 06 08 03 | 04 00 | 01 00 00 00 | Set Interleaved 2 of 5 (ITF5) to 6 digit length | 57 00 00 06 08 03 00 00 00 04 00 01 00 00 00 00 C5 21 50 41 |
| 06 08 03 | 04 00 | 02 00 00 00 | Set Interleaved 2 of 5 (ITF5) to 8 digit length | 57 00 00 06 08 03 00 00 00 04 00 02 00 00 00 00 C5 65 50 41 |
| 06 08 03 | 04 00 | 03 00 00 00 | Set Interleaved 2 of 5 (ITF5) to 10 digit length | 57 00 00 06 08 03 00 00 00 04 00 03 00 00 00 00 C4 99 50 41 |
| 06 08 03 | 04 00 | 04 00 00 00 | Set Interleaved 2 of 5 (ITF5) to 12 digit length | 57 00 00 06 08 03 00 00 00 04 00 04 00 00 00 00 C5 ED 50 41 |
| 06 08 03 | 04 00 | 05 00 00 00 | Set Interleaved 2 of 5 (ITF5) to 14 digit length | 57 00 00 06 08 03 00 00 00 04 00 05 00 00 00 00 C4 11 50 41 |

| | | | | |
|----------------|-------|-------------|--|---|
| 06 08 03 | 04 00 | 06 00 00 00 | Set Interleaved 2 of 5 (ITF5) to 16 digit length | 57 00 00 06 08 03 00 00 00 04 00 06 00 00 00 C4 55 50 41 |
| 06 08 03 | 04 00 | 07 00 00 00 | Set Interleaved 2 of 5 (ITF5) to 18 digit length | 57 00 00 06 08 03 00 00 00 04 00 07 00 00 00 C5 A9 50 41 |
| 06 08 03 | 04 00 | 08 00 00 00 | Set Interleaved 2 of 5 (ITF5) to 20 digit length | 57 00 00 06 08 03 00 00 00 04 00 08 00 00 00 C6 BD 50 41 |
| 06 08 03 | 04 00 | 09 00 00 00 | Set Interleaved 2 of 5 (ITF5) to 22 digit length | 57 00 00 06 08 03 00 00 00 04 00 09 00 00 00 C7 41 50 41 |
| 06 08 03 | 04 00 | 0A 00 00 00 | ISet Interleaved 2 of 5 (ITF5) to 24 digit length | 57 00 00 06 08 03 00 00 00 04 00 0A 00 00 00 C7 05 50 41 |
| 06 08 03 | 04 00 | 0B 00 00 00 | Interleaved 2 of 5 (ITF5) Any Length | 57 00 00 06 08 03 00 00 00 04 00 0B 00 00 00 C6 F9 50 41 |
| 06 08 04 | 02 00 | 08 0C | Interleaved 2 of 5 (ITF5) Set length Range 8-12 | 57 00 00 06 08 04 00 00 00 02 00 08 0C 4B 46 50 41 |
| 06 09 01 | 04 00 | 01 00 00 00 | Enable Industrial 2 of 5 | 57 00 00 06 09 01 00 00 00 04 00 01 00 00 00 60 17 50 41 |
| 06 09 01 | 04 00 | 00 00 00 00 | Disable Industrial 2 of 5 | 57 00 00 06 09 01 00 00 00 04 00 00 00 00 00 61 EB 50 41 |
| 06 09 02 | 02 00 | 08 0C | Example: Industrial 2 of 5 Set Length Range 8-12 | 57 00 00 06 09 02 00 00 00 02 00 08 0C C6 FC 50 41 |

| | | | | |
|----------------|-------|-------------|--|---|
| 06 0A 01 | 04 00 | 01 00 00 00 | Enable Matrix 2 of 5 | 57 00 00 06 0A 01 00 00 00 04 00 01 00 00 00 6F 53 50 41 |
| 06 0A 01 | 04 00 | 00 00 00 00 | Disable Matrix 2 of 5 | 57 00 00 06 0A 01 00 00 00 04 00 00 00 00 00 6E AF 50 41 |
| 06 0A 02 | 02 00 | 08 0C | Example : Matrix 2 of 5 Length Range 8-12 | 57 00 00 06 0A 02 00 00 00 02 00 08 0C D2 0C 50 41 |
| 06 0B 01 | 04 00 | 01 00 00 00 | Enable Code 93 | 57 00 00 06 0B 01 00 00 00 04 00 01 00 00 00 6B AF 50 41 |
| 06 0B 01 | 04 00 | 00 00 00 00 | Disable Code 93 | 57 00 00 06 0B 01 00 00 00 04 00 00 00 00 00 6A 53 50 41 |
| 06 0B 02 | 02 00 | 08 0C | Example : Code 93 Set Length Range 8-12 | 57 00 00 06 0B 02 00 00 00 02 00 08 0C DF 9C 50 41 |
| 06 0C 01 | 04 00 | 01 00 00 00 | Enable Code 11 | 57 00 00 06 0C 01 00 00 00 04 00 01 00 00 00 71 DB 50 41 |
| 06 0C 01 | 04 00 | 00 00 00 00 | Disable Code 11 | 57 00 00 06 0C 01 00 00 00 04 00 00 00 00 00 70 27 50 41 |
| 06 0C 02 | 04 00 | 01 00 00 00 | Do not Transmit Code 11 Check Digit | 57 00 00 06 0C 02 00 00 00 04 00 01 00 00 00 81 D4 50 41 |
| 06 0C 02 | 04 00 | 00 00 00 00 | Transmit Code 11 Check Digit | 57 00 00 06 0C 02 00 00 00 04 00 00 00 00 00 80 28 50 41 |

| | | | | |
|----------------|-------|-------------|---|---|
| 06 0C 03 | 04 00 | 00 00 00 00 | Disable Code 11 Check Digit | 57 00 00 06 0C 03 00 00 00 04 00 00 00 00 00 D1 ED 50 41 |
| 06 0C 03 | 04 00 | 01 00 00 00 | Enable Code 11 1 Check Digit | 57 00 00 06 0C 03 00 00 00 04 00 01 00 00 00 D0 11 50 41 |
| 06 0C 03 | 04 00 | 02 00 00 00 | Enable Code 11 2 Check Digit | 57 00 00 06 0C 03 00 00 00 04 00 02 00 00 00 D0 55 50 41 |
| 06 0C 04 | 02 00 | 08 0C | Example: Set Length Range 8-12 to Code 11 | 57 00 00 06 0C 04 00 00 00 02 00 08 0C 79 86 50 41 |
| 06 0D 01 | 04 00 | 01 00 00 00 | Enable Code 128 | 57 00 00 06 0D 01 00 00 00 04 00 01 00 00 00 75 27 50 41 |
| 06 0D 01 | 04 00 | 00 00 00 00 | Disable Code 128 | 57 00 00 06 0D 01 00 00 00 04 00 00 00 00 00 74 DB 50 41 |
| 06 0D 02 | 02 00 | 08 0C | Example: Set Length Range 8-12 to Code 128 | 57 00 00 06 0D 02 00 00 00 02 00 08 0C F4 3C 50 41 |
| 06 0E 00 | 04 00 | 01 00 00 00 | Enable GS1-128 | 57 00 00 06 0E 00 00 00 00 04 00 01 00 00 00 2B A6 50 41 |
| 06 0E 00 | 04 00 | 00 00 00 00 | Disable GS1-128 | 57 00 00 06 0E 00 00 00 00 04 00 00 00 00 00 2A 5A 50 41 |
| 06 10 01 | 04 00 | 01 00 00 00 | Enable UPC-A | 57 00 00 06 10 01 00 00 00 04 00 01 00 00 00 1A 4B 50 41 |

| | | | | |
|----------------|-------|-------------|--------------------------------------|--|
| 06 10 01 | 04 00 | 00 00 00 00 | Disable UPC-A | 57 00 00 06 10 01 00 00 00 04 00 00 00 00 00 00 1B B7 50 41 |
| 06 10 02 | 04 00 | 01 00 00 00 | Transmit UPC-A Check Digit | 57 00 00 06 10 02 00 00 00 04 00 01 00 00 00 00 EA 44 50 41 |
| 06 10 02 | 04 00 | 00 00 00 00 | Do not Transmit UPC-A Check Digit | 57 00 00 06 10 02 00 00 00 04 00 00 00 00 00 00 EB B8 50 41 |
| 06 10 03 | 04 00 | 01 00 00 00 | Convert UPC-A to EAN-13 | 57 00 00 06 10 03 00 00 00 04 00 01 00 00 00 00 BB 81 50 41 |
| 06 10 03 | 04 00 | 00 00 00 00 | Convert UPC-A to EAN-13 | 57 00 00 06 10 03 00 00 00 04 00 00 00 00 00 00 BA 7D 50 41 |
| 06 11 01 | 04 00 | 01 00 00 00 | Enable UPC-E | 57 00 00 06 11 01 00 00 00 04 00 01 00 00 00 00 1E B7 50 41 |
| 06 11 01 | 04 00 | 00 00 00 00 | Disable UPC-E | 57 00 00 06 11 01 00 00 00 04 00 00 00 00 00 00 1F 4B 50 41 |
| 06 11 02 | 04 00 | 01 00 00 00 | Transmit UPC-E Check Digit | 57 00 00 06 11 02 00 00 00 04 00 01 00 00 00 00 EE B8 50 41 |
| 06 11 02 | 04 00 | 00 00 00 00 | Do not Transmit UPC-E Check Digit | 57 00 00 06 11 02 00 00 00 04 00 00 00 00 00 00 EF 44 50 41 |
| 06 11 03 | 04 00 | 01 00 00 00 | Convert UPC-E to UPC-A | 57 00 00 06 11 03 00 00 00 04 00 01 00 00 00 00 BF 7D 50 41 |

| | | | | |
|----------------|-------|-------------|--------------------------------|--|
| 06 11 03 | 04 00 | 00 00 00 00 | Convert UPC-E to UPC-A | 57 00 00 06 11 03 00 00 00 04 00 00 00 00 00 00 BE 81 50 41 |
| 06 12 00 | 04 00 | 01 00 00 00 | Enable EAN/JAN-8 | 57 00 00 06 12 00 00 00 00 04 00 01 00 00 00 00 40 36 50 41 |
| 06 12 00 | 04 00 | 00 00 00 00 | Disable EAN/JAN-8 | 57 00 00 06 12 00 00 00 00 04 00 00 00 00 00 00 41 CA 50 41 |
| 06 13 01 | 04 00 | 01 00 00 00 | Enable EAN/JAN-13 | 57 00 00 06 13 01 00 00 00 04 00 01 00 00 00 00 15 0F 50 41 |
| 06 13 01 | 04 00 | 00 00 00 00 | Disable EAN/JAN-13 | 57 00 00 06 13 01 00 00 00 04 00 00 00 00 00 00 14 F3 50 41 |
| 06 13 02 | 04 00 | 01 00 00 00 | Convert EAN13 to ISBN | 57 00 00 06 13 02 00 00 00 04 00 01 00 00 00 00 E5 00 50 41 |
| 06 13 02 | 04 00 | 00 00 00 00 | Do Not Convert EAN13 to ISBN | 57 00 00 06 13 02 00 00 00 04 00 00 00 00 00 00 E4 FC 50 41 |
| 06 13 03 | 04 00 | 01 00 00 00 | Convert EAN13 to ISSN | 57 00 00 06 13 03 00 00 00 04 00 01 00 00 00 00 B4 C5 50 41 |
| 06 13 03 | 04 00 | 00 00 00 00 | Do not Convert EAN13 to ISSN | 57 00 00 06 13 03 00 00 00 04 00 00 00 00 00 00 B5 39 50 41 |
| 06 14 00 | 04 00 | 00 00 00 00 | Ignore UPC/EAN/JAN Supplements | 57 00 00 06 14 00 00 00 00 04 00 00 00 00 00 00 5F 42 50 41 |

| | | | | |
|----------------|-------|-------------|---|---|
| 06 14 00 | 04 00 | 01 00 00 00 | Decode UPC/EAN/JAN Supplementals | 57 00 00 06 14 00 00 00 00 04 00 01 00 00 00 5E BE 50 41 |
| 06 14 00 | 04 00 | 02 00 00 00 | Self-describe UPC/EAN/JAN Supplementals | 57 00 00 06 14 00 00 00 00 04 00 02 00 00 00 5E FA 50 41 |
| 06 15 01 | 04 00 | 01 00 00 00 | Enable GS1 DataBar | 57 00 00 06 15 01 00 00 00 04 00 01 00 00 00 0B 87 50 41 |
| 06 15 01 | 04 00 | 00 00 00 00 | Disable GS1 DataBar | 57 00 00 06 15 01 00 00 00 04 00 00 00 00 00 0A 7B 50 41 |
| 06 15 02 | 04 00 | 01 00 00 00 | Enable GS1 DataBar Limited | 57 00 00 06 15 02 00 00 00 04 00 01 00 00 00 FB 88 50 41 |
| 06 15 02 | 04 00 | 00 00 00 00 | Disable GS1 DataBar Limited | 57 00 00 06 15 02 00 00 00 04 00 00 00 00 00 FA 74 50 41 |
| 06 15 03 | 04 00 | 01 00 00 00 | Enable GS1 DataBar Expanded | 57 00 00 06 15 03 00 00 00 04 00 01 00 00 00 AA 4D 50 41 |
| 06 15 03 | 04 00 | 00 00 00 00 | Disable GS1 DataBar Expanded | 57 00 00 06 15 03 00 00 00 04 00 00 00 00 00 AB B1 50 41 |
| 06 15 04 | 04 00 | 01 00 00 00 | Enable GS1 DATABAR(RSS14) Preamble | 57 00 00 06 15 04 00 00 00 04 00 01 00 00 00 1B 97 50 41 |
| 06 15 04 | 04 00 | 00 00 00 00 | Disable GS1 DATABAR(RSS14) Preamble | 57 00 00 06 15 04 00 00 00 04 00 00 00 00 00 1A 6B 50 41 |

| | | | | |
|----------------|-------|-------------|---|---|
| 06 15 05 | 04 00 | 01 00 00 00 | Enable GS1 DATABAR LIMITED Preamble | 57 00 00 06 15 05 00 00 00 04 00 01 00 00 00 4A 52 50 41 |
| 06 15 05 | 04 00 | 00 00 00 00 | Disable GS1 DATABAR LIMITED Preamble | 57 00 00 06 15 05 00 00 00 04 00 00 00 00 00 4B AE 50 41 |
| 06 16 00 | 04 00 | 01 00 00 00 | Enable PDF417 | 57 00 00 06 16 00 00 00 00 04 00 01 00 00 00 55 06 50 41 |
| 06 16 00 | 04 00 | 00 00 00 00 | Disable PDF417 | 57 00 00 06 16 00 00 00 00 04 00 00 00 00 00 54 FA 50 41 |
| 06 17 00 | 04 00 | 01 00 00 00 | Enable Micro PDF417 | 57 00 00 06 17 00 00 00 00 04 00 01 00 00 00 51 FA 50 41 |
| 06 17 00 | 04 00 | 00 00 00 00 | Disable Micro PDF417 | 57 00 00 06 17 00 00 00 00 04 00 00 00 00 00 50 06 50 41 |
| 06 18 01 | 04 00 | 01 00 00 00 | Enable QR | 57 00 00 06 18 01 00 00 00 04 00 01 00 00 00 30 2B 50 41 |
| 06 18 01 | 04 00 | 00 00 00 00 | Disable QR | 57 00 00 06 18 01 00 00 00 04 00 00 00 00 00 31 D7 50 41 |
| 06 18 02 | 04 00 | 01 00 00 00 | Enable QR URL | 57 00 00 06 18 02 00 00 00 04 00 01 00 00 00 C0 24 50 41 |
| 06 18 02 | 04 00 | 00 00 00 00 | Disable QR URL | 57 00 00 06 18 02 00 00 00 04 00 00 00 00 00 C1 D8 50 41 |

| | | | | |
|----------------|-------|-------------|-------------------------------------|---|
| 06 19 00 | 04 00 | 01 00 00 00 | Enable Micro QR | 57 00 00 06 19 00 00 00 00 04 00 01 00 00 00 65 12 50 41 |
| 06 19 00 | 04 00 | 00 00 00 00 | Disable Micro QR | 57 00 00 06 19 00 00 00 00 04 00 00 00 00 00 64 EE 50 41 |
| 06 1A 00 | 04 00 | 01 00 00 00 | Enable Data Matrix | 57 00 00 06 1A 00 00 00 00 04 00 01 00 00 00 6A 56 50 41 |
| 06 1A 00 | 04 00 | 00 00 00 00 | Disable Data Matrix | 57 00 00 06 1A 00 00 00 00 04 00 00 00 00 00 6B AA 50 41 |
| 06 1B 00 | 04 00 | 01 00 00 00 | Enable Aztec | 57 00 00 06 1B 00 00 00 00 04 00 01 00 00 00 6E AA 50 41 |
| 06 1B 00 | 04 00 | 00 00 00 00 | Disable Aztec | 57 00 00 06 1B 00 00 00 00 04 00 00 00 00 00 6F 56 50 41 |
| 06 1E 01 | 04 00 | 01 00 00 00 | Enable msiplessey | 57 00 00 06 1E 01 00 00 00 04 00 01 00 00 00 2E A3 50 41 |
| 06 1E 01 | 04 00 | 00 00 00 00 | Disable msiplessey | 57 00 00 06 1E 01 00 00 00 04 00 00 00 00 00 2F 5F 50 41 |
| 06 1E 02 | 04 00 | 00 00 00 00 | Disable msiplessey Check Digit | 57 00 00 06 1E 02 00 00 00 04 00 00 00 00 00 DF 50 50 41 |
| 06 1E 02 | 04 00 | 01 00 00 00 | Set msiplessey Check Digit MOD10 | 57 00 00 06 1E 02 00 00 00 04 00 01 00 00 00 DE AC 50 41 |

| | | | | | |
|--|----------------|-------|-------------|--|--|
| | 06 1E 02 | 04 00 | 02 00 00 00 | Set msiplessey Check Digit MOD10/MOD10 | 57 00 00 06 1E 02 00 00 00 04 00 02 00 00 00 00 DE E8 50 41 |
| | 06 1E 02 | 04 00 | 03 00 00 00 | Set msiplessey Check Digit MOD10/MOD11 | 57 00 00 06 1E 02 00 00 00 04 00 03 00 00 00 00 DF 14 50 41 |
| | 06 1E 03 | 02 00 | 08 0C | Example Set Length Range 8-12 to msiplessey | 57 00 00 06 1E 03 00 00 00 02 00 08 0C EC C0 50 41 |
| | 06 1F 00 | 04 00 | 01 00 00 00 | Enable hanxi code | 57 00 00 06 1F 00 00 00 00 04 00 01 00 00 00 00 7B 9A 50 41 |
| | 06 1F 00 | 04 00 | 00 00 00 00 | Disable hanxi code | 57 00 00 06 1F 00 00 00 00 04 00 00 00 00 00 00 7A 66 50 41 |

Appendix

Appendix 1 Bar Code Types

| Bar Code Types | CODE ID | | AIM ID |
|-------------------------------------|---------|---|--------|
| | HEX | | ID |
| All Bar Code Types | 0x99 | | |
| Codabar | 0x61 | a |]F0 |
| Code 11 | 0x68 | h |]H1 |
| Code 128(Including GS1 128)、GS1-128 | 0x6A | j |]C0 |
| ISBT 128 | 0x6A | j |]C0 |
| Code 32 | 0x3C | < |]X0 |
| Code 39 | 0x62 | b |]A0 |
| Code 93 | 0x69 | i |]G0 |
| EAN | | | |
| EAN-13(including ISBN) | 0x64 | d |]E0 |
| EAN-8 | 0x44 | D |]E4 |
| GS1 | | | |
| GS1 DataBar | 0x79 | y |]e0 |
| GS1 DataBar Limited | 0x7B | { |]e0 |
| GS1 DataBar Expanded | 0x7D | } |]e0 |
| 2 of 5 | | | |

| | | | |
|--------------------|------|---|-----|
| Interleaved 2 of 5 | 0x65 | e |]I0 |
|--------------------|------|---|-----|

| | | | |
|----------------------------|------|---|-----|
| Matrix 2 of 5 | 0x6D | m |]X0 |
| Straight 2 of 5 Industrial | 0x66 | f |]S0 |
| MSI | 0x67 | g |]M1 |
| UPC | | | |
| UPC-A | 0x63 | c |]E0 |
| UPC-E | 0x45 | E |]E0 |
| Aztec Code | 0x7A | z |]z0 |
| Han Xin | 0x48 | H |]X0 |
| Codablock F | 0x6A | j |]C0 |
| Data Matrix | 0x77 | w |]d1 |
| PDF417、Micro PDF417 | 0x72 | r |]L0 |
| QR、Micro QR | 0x73 | s |]Q1 |

Appendix 2 Control Characters

| char | hex | Not converted | value | Keystroke |
|------------------------------|------|----------------|-------|-----------|
| NUL (Null char.) | 0x00 | Null | 0x00 | Ctrl+2 |
| SOH (Start of Header) | 0x01 | Keypad Enter | 0x58 | Ctrl+A |
| STX (Start of Text) | 0x02 | Caps Lock | 0x39 | Ctrl+B |
| ETX (End of Text) | 0x03 | Null | 0x00 | Ctrl+C |
| EOT (End of Transmission) | 0x04 | Null | 0x00 | Ctrl+D |
| ENQ (Enquiry) | 0x05 | Null | 0x00 | Ctrl+E |
| ACK (Acknowledgment) | 0x06 | Null | 0x00 | Ctrl+F |
| BEL (Bell) | 0x07 | Enter | 0x28 | Ctrl+G |
| BS (Backspace) | 0x08 | Left Arrow | 0x50 | Ctrl+H |
| HT (Horizontal Tab) | 0x09 | Horizontal Tab | 0x2b | Ctrl+I |
| LF (Line Feed) | 0x0a | Down Arrow | 0x51 | Ctrl+J |
| VT (Vertical Tab) | 0x0b | Vertical Tab | 0x2b | Ctrl+K |
| FF (Form Feed) | 0x0c | Backspace | 0x2a | Ctrl+L |
| CR (Carriage Return) | 0x0d | Enter | 0x28 | Ctrl+M |
| SO (Shift Out) | 0x0e | Insert | 0x49 | Ctrl+N |
| SI (Shift In) | 0x0f | Esc | 0x29 | Ctrl+O |
| DLE (Data Link Escape) | 0x10 | F11 | 0x44 | Ctrl+P |
| DC1 (XON) (Device Control 1) | 0x11 | Home | 0x4a | Ctrl+Q |

| | | | | |
|--------------------------------|------|--------------|-----------|--------|
| DC2 (Device Control 2) | 0x12 | Print Screen | 0x46 | Ctrl+R |
| DC3 (XOFF) (Device Control 3) | 0x13 | Delete | 0x4c | Ctrl+S |
| DC4 (Device Control 4) | 0x14 | tab+shift | 0x2b,0xe1 | Ctrl+T |
| NAK (Negative Acknowledgement) | 0x15 | F12 | 0x45 | Ctrl+U |
| SYN (Synchronous Idle) | 0x16 | F1 | 0x3a | Ctrl+V |
| ETB (End of Trans. Block) | 0x17 | F2 | 0x3b | Ctrl+W |
| CAN (Cancel) | 0x18 | F3 | 0x3c | Ctrl+X |
| EM (End of Medium) | 0x19 | F4 | 0x3d | Ctrl+Y |
| SUB (Substitute) | 0x1a | F5 | 0x3e | Ctrl+Z |
| ESC (Escape) | 0x1b | F6 | 0x3f | Ctrl+[|
| FS (File Separator) | 0x1c | F7 | 0x40 | Ctrl+\ |
| GS (Group Separator) | 0x1d | F8 | 0x41 | Ctrl+] |
| RS (Request to Send) | 0x1e | F9 | 0x42 | Ctrl+6 |
| US (Unit Separator) | 0x1f | F10 | 0x43 | Ctrl+- |

Appendix 3 ASCII Characters

Characters in yellow ground are control characters; characters in white ground are visible characters.

| bin | Dec | Hex | char |
|------|-----|-----|----------------------------|
| 0 | 0 | 0 | NUL (NULL) |
| 1 | 1 | 1 | SOH (Start Of Headling) |
| 10 | 2 | 2 | STX (Start Of Text) |
| 11 | 3 | 3 | ETX (End Of Text) |
| 100 | 4 | 4 | EOT (End Of Transmission) |
| 101 | 5 | 5 | ENQ (Enquiry) |
| 110 | 6 | 6 | ACK (Acknowledge) |
| 111 | 7 | 7 | BEL (Bell) |
| 1000 | 8 | 8 | BS (Backspace) |
| 1001 | 9 | 9 | HT (Horizontal Tab) |
| 1010 | 10 | 0A | LF/NL(Line Feed/New Line) |
| 1011 | 11 | 0B | VT (Vertical Tab) |
| 1100 | 12 | 0C | FF/NP (Form Feed/New Page) |
| 1101 | 13 | 0D | CR (Carriage Return) |
| 1110 | 14 | 0E | SO (Shift Out) |

| | | | |
|-------|----|----|--|
| 1111 | 15 | 0F | SI (Shift In) |
| 10000 | 16 | 10 | DLE (Data Link Escape) |
| 10001 | 17 | 11 | DC1/XON |
| | | | (Device Control 1/Transmission On) |
| 10010 | 18 | 12 | DC2 (Device Control 2) |
| 10011 | 19 | 13 | DC3/XOFF |
| | | | (Device Control 3/Transmission Off) |
| 10100 | 20 | 14 | DC4 (Device Control 4) |
| 10101 | 21 | 15 | NAK (Negative Acknowledge) |
| 10110 | 22 | 16 | SYN (Synchronous Idle) |
| 10111 | 23 | 17 | ETB (End of Transmission Block) |
| 11000 | 24 | 18 | CAN (Cancel) |
| 11001 | 25 | 19 | EM (End of Medium) |
| 11010 | 26 | 1A | SUB (Substitute) |
| 11011 | 27 | 1B | ESC (Escape) |

| | | | |
|--------|----|----|-----------------------|
| 11100 | 28 | 1C | FS (File Separator) |
| 11101 | 29 | 1D | GS (Group Separator) |
| 11110 | 30 | 1E | RS (Record Separator) |
| 11111 | 31 | 1F | US (Unit Separator) |
| 100000 | 32 | 20 | (Space) |
| 100001 | 33 | 21 | ! |
| 100010 | 34 | 22 | " |
| 100011 | 35 | 23 | # |
| 100100 | 36 | 24 | \$ |
| 100101 | 37 | 25 | % |
| 100110 | 38 | 26 | & |
| 100111 | 39 | 27 | ' |
| 101000 | 40 | 28 | (|
| 101001 | 41 | 29 |) |
| 101010 | 42 | 2A | * |
| 101011 | 43 | 2B | + |
| 101100 | 44 | 2C | , |
| 101101 | 45 | 2D | - |
| 101110 | 46 | 2E | . |
| 101111 | 47 | 2F | / |

| | | | |
|---------|----|----|---|
| 110000 | 48 | 30 | 0 |
| 110001 | 49 | 31 | 1 |
| 110010 | 50 | 32 | 2 |
| 110011 | 51 | 33 | 3 |
| 110100 | 52 | 34 | 4 |
| 110101 | 53 | 35 | 5 |
| 110110 | 54 | 36 | 6 |
| 110111 | 55 | 37 | 7 |
| 111000 | 56 | 38 | 8 |
| 111001 | 57 | 39 | 9 |
| 111010 | 58 | 3A | : |
| 111011 | 59 | 3B | ; |
| 111100 | 60 | 3C | < |
| 111101 | 61 | 3D | = |
| 111110 | 62 | 3E | > |
| 111111 | 63 | 3F | ? |
| 1000000 | 64 | 40 | @ |
| 1000001 | 65 | 41 | A |
| 1000010 | 66 | 42 | B |
| 1000011 | 67 | 43 | C |

| | | | |
|---------|----|----|---|
| 1000100 | 68 | 44 | D |
| 1000101 | 69 | 45 | E |
| 1000110 | 70 | 46 | F |
| 1000111 | 71 | 47 | G |
| 1001000 | 72 | 48 | H |
| 1001001 | 73 | 49 | I |
| 1001010 | 74 | 4A | J |
| 1001011 | 75 | 4B | K |
| 1001100 | 76 | 4C | L |
| 1001101 | 77 | 4D | M |
| 1001110 | 78 | 4E | N |
| 1001111 | 79 | 4F | O |
| 1010000 | 80 | 50 | P |
| 1010001 | 81 | 51 | Q |
| 1010010 | 82 | 52 | R |
| 1010011 | 83 | 53 | S |
| 1010100 | 84 | 54 | T |
| 1010101 | 85 | 55 | U |
| 1010110 | 86 | 56 | V |
| 1010111 | 87 | 57 | W |

| | | | |
|---------|-----|----|---|
| 1011000 | 88 | 58 | X |
| 1011001 | 89 | 59 | Y |
| 1011010 | 90 | 5A | Z |
| 1011011 | 91 | 5B | [|
| 1011100 | 92 | 5C | \ |
| 1011101 | 93 | 5D |] |
| 1011110 | 94 | 5E | ^ |
| 1011111 | 95 | 5F | _ |
| 1100000 | 96 | 60 | ` |
| 1100001 | 97 | 61 | a |
| 1100010 | 98 | 62 | b |
| 1100011 | 99 | 63 | c |
| 1100100 | 100 | 64 | d |
| 1100101 | 101 | 65 | e |
| 1100110 | 102 | 66 | f |
| 1100111 | 103 | 67 | g |
| 1101000 | 104 | 68 | h |
| 1101001 | 105 | 69 | i |
| 1101010 | 106 | 6A | j |
| 1101011 | 107 | 6B | k |

| | | | |
|---------|-----|----|--------------|
| 1101100 | 108 | 6C | l |
| 1101101 | 109 | 6D | m |
| 1101110 | 110 | 6E | n |
| 1101111 | 111 | 6F | o |
| 1110000 | 112 | 70 | p |
| 1110001 | 113 | 71 | q |
| 1110010 | 114 | 72 | r |
| 1110011 | 115 | 73 | s |
| 1110100 | 116 | 74 | t |
| 1110101 | 117 | 75 | u |
| 1110110 | 118 | 76 | v |
| 1110111 | 119 | 77 | w |
| 1111000 | 120 | 78 | x |
| 1111001 | 121 | 79 | y |
| 1111010 | 122 | 7A | z |
| 1111011 | 123 | 7B | { |
| 1111100 | 124 | 7C | |
| 1111101 | 125 | 7D | } |
| 1111110 | 126 | 7E | ~ |
| 1111111 | 127 | 7F | DEL (Delete) |

Revision

| Version | Description | Date |
|---------|-----------------|------------|
| V1.0 | Initial Release | 2023.06.08 |